

Appendix 5: Multi-Card Co-Located Operation

Instruction Manual

Version: V2.04

Update Date: 2023.07.01

CONTENTS

1. Direct Use of Application Software	1
2. Secondary Development	4

1. Direct Use of Application Software

Multiple USBCAN bus adapters/CANalyst-II analyzers etc. are used on the same PC. The use process is as follows:

1. Plug them into the same computer, and you will be prompted to install the new hardware driver. the USBCAN Bus Adapter/CANalyst-II Analyzer uses the same USB driver, and a computer only needs to install the driver once. If you plug in the computer, the device manager can already load the driver normally, you can directly skip this step.

2. Open "USB_CAN TOOL.exe", select the device type you want to open in the "Device Type" menu, and then click the menu: "Device Operation" -> "Start Device". "Start Device" to open the "Open USB Device dialog box", as shown below:




Figure 1 Selecting a USB-CAN Adapter in the Computer

Select the device to be opened, click "Open", and then the corresponding software operation can be.

3. Create a copy:

Find the USB_CAN TOOL software installation directory, the default is C:\Program Files (x86)\USB_CAN TOOL, the USB_CAN TOOL folder according to the need to create a copy (copy), respectively, the USB_CAN TOOL.exe to create a desktop shortcut, and renamed.



4 In turn, open a copy of the "USB_CAN TOOL.exe", in the "Device Type" menu, select the type of device to open, and then click on the menu: "Device Operations "->" start the device "to open" open "open the USB device dialog box", the following chart:




Figure 2 Selecting another USB-CAN Adapter in the Computer

Select the device you want to open, click "Open", and then proceed with the corresponding software operation.

Note: One "USB_CAN TOOL.exe" can only load one USB_CAN-2(x) or CANalyst-II analyzer, the drop-down box of the open device list will show the serial numbers of all USB_CAN-2(x) or CANalyst-II analyzers connected to the computer. The serial numbers of all USB_CAN-2(x) or CANalyst-II analyzers connected to the computer will be displayed in the Open Device List drop-down box (those that have already been loaded are shown blank and do not have a serial number. Only serial numbers that are not currently loaded can be selected.) against the serial number on the label on the back of the USBCAN adapter and turn it on. When opening the device behind it, you must select a different device model than the one previously selected.

Note: A computer can support up to 50 or more USB_CAN devices.




Figure 3 Multiple Copies of USB-CAN Tool Running on the Same Computer with Multiple CAN Adapters Open

2. Secondary Development

Secondary development, refer to the *"4. Interface Function Library (secondary development library) manual.pdf"* in the VCI_FindUsbDevice2 function, at the very beginning of the program, call the function, you can scan out the current number of computers available on the USBCAN, or CAN analyzer devices. Function return value is the total number of structures in the array, save the card information, within the serial number.